



INSTRUCTIONS FOR DISINFECTION USING BLEACH SOLUTIONS OF SPD1374 BLEACH TABLETS

HOW TO USE:

STEP 1

Wear appropriate PPE:
Gloves, Apron and Safety Glasses.
If in a confined space, open
a window for ventilation.

STEP 2

Fill the bottle with cold or warm
water (max. 30°C) to shoulder
height for 1 litre volume.

STEP 3

Drop in the required number
of tablets and allow to dissolve,
shaking the bottle prior to use.

STEP 4

Record the solution strength
(PPM) on the label.

STEP 5

Apply the solution liberally over
the surface using the push-pull
cap or trigger spray head.

STEP 6

Observe the indicated contact
times for the required
antimicrobial activity.

STEP 7

Keep prepared solution for no
longer than 24 hours. Dispose
of residual solution into an
appropriate drain, sluice or
sink with running water.

SPD1374 3.25g tablets
contain 1.67g NaDCC per
tablet and are:

Bactericidal according to:
EN1276, EN13727, EN16615
Yeasticidal according to:
EN1650, EN13624, EN16615
Virucidal according to:
EN14476

Sporicidal against *C. difficile*
according to:
EN13704, EN17126



ROUTINE DISINFECTION FOR PRE-CLEANED SURFACES:

Dissolve 1 tablet in 1 litre water for a
1,000 PPM available chlorine solution.

Apply solution using the push-pull
cap or spray, fully wetting the surface.

Allow contact time:

Bactericidal, Yeasticidal,
Virucidal activity: 5 minutes.

Sporicidal activity (for known or suspected
Clostridium difficile contamination): 10 minutes.

MANAGEMENT OF BLOOD SPILLAGES (OTHER THAN URINE/ FAECES/ VOMIT/ SPUTUM):

Dissolve 10 tablets in 1 litre water for a
10,000 PPM available chlorine solution.

Cover spillage with paper towels.

Apply solution using the push-pull
cap, fully wetting the surface.

Allow 5 minutes contact time. Remove
and dispose of spill material to clinical waste.

Clean the area with PLAT148 General Purpose
Neutral Detergent or PLAT980 All Purpose Cleaner.

MANAGEMENT OF SPILLS CONTAINING ONLY URINE/ FAECES/ VOMIT/ SPUTUM:

Dissolve 1 tablet in 1 litre water for
a 1,000 PPM available chlorine solution.

Soak up the spillage using paper towels.

Discard the gross contamination to clinical waste.

Apply solution using the push-pull
cap, fully wetting the surface.

Allow 5 minutes contact time.

Clean the area with PLAT148 General Purpose
Neutral Detergent or PLAT980 All Purpose Cleaner.

SPEARHEAD®


Southcraig Avenue, Kilmarnock KA3 6BQ

0345 180 1800

sales@spearheadhealthcare.com
spearheadhealthcare.com

TAKING CARE OF CARE

MANAGEMENT OF BLOOD & BODY FLUID SPILLS SPD1374 BLEACH TABLETS



SPEARHEAD®

Southcraig Avenue, Kilmarnock KA3 6BQ

0345 180 1800

sales@spearheadhealthcare.com
spearheadhealthcare.com

**TAKING
CARE
OF
CARE**